



Tech Info Library

Macintosh Application Environment: Print Troubleshooting (5/94)

Revised: 5/20/94
Security: Everyone

Macintosh Application Environment: Print Troubleshooting (5/94)

=====

Article Created: 16 May 1994

TOPIC -----

This article provides some ideas and helpful hints when troubleshooting printing problems with Macintosh Application Environment (MAE).

DISCUSSION -----

Before you can print from MAE, UNIX printing must be correctly configured on the workstation. In addition, MAE only supports printing to Postscript printers, since Postscript is the only page description language commonly available on UNIX workstations. If there is no Postscript printer available, then you will not be able to print from MAE.

If you have never printed on your workstation, or are not sure of the types of printers available, see your system administrator, who should be able to help you solve problems with the UNIX print spooler configuration, based on the error messages displayed in the X window where you started MAE.

For flexibility with MAE, you can specify any UNIX command you choose for printing a generated PostScript file. The printing sub-system takes the user-specified command, and passes it to a UNIX shell, generating a command line similar to:

```
cat MAE.ps | USER_COMMAND
```

MAE.ps is the PostScript file generated by MAE, and USER_COMMAND is what you typed into the Setup dialog in the Chooser. Thus, the command that is used for printing reads its "standard input" to gather the PostScript file for printing. The command specified MUST be able to read the file to be printed from its standard input. Both lp and lpr (standard printing systems on UNIX workstations) have this functionality. We suggest testing a print command from the UNIX command line before entering it in a print command description in the Chooser. You should test the command by having it read its standard input, as above. If you are having problems getting a print command to work, you should

try to print from the UNIX command line.

Nothing comes out of the printer

- Have never printed from the UNIX workstation

The underlying UNIX spooling system must be set up before printing from MAE. See your system administrator, or read the documentation that came with your workstation. The most common UNIX spoolers are lp and lpr.

- Have printed from the UNIX workstation
- 1) Check the X window in which MAE was started. MAE displays any error or status messages in this window. The error messages can provide useful information about why printing isn't working. (For example, "lp: unknown printer <printer name>", or "lp: host NAME is refusing permission", or "lp: no space left on device"). Here are some common problems:
 - Remote machine is unavailable.
 - Permission has not been granted for the your machine (for remote printing via lpd).
 - There is no space left in the spooling directories (your home directory, /usr/spool).
 - The printer is not accepting requests (Type "lpstat -a" to see if this is the case. "Not accepting requests" or "disabled" means that the spooler won't use that printer.)

A message similar to: "request id is Silence-0 (standard input)" is normal. This means that the UNIX spooler has accepted the print request. It also indicates which printer got the request.

- 2) Have you ever printed from MAE? (You have to go into the Chooser and create a print command before printing in MAE.) If you've never been able to print, print a text file from UNIX, and after verifying that it worked, type the exact same command into the Chooser window without the file name. If this doesn't work, click the "File" radio button on the right, inside a dashed box labeled "destination". This causes LprWriter (just like LaserWriter 8) to save the output to a file instead of sending it to a printer. A standard file dialog pops up, asking where to put the file. After the file is saved, go to a UNIX window and try to print the file. This provides you with a print command that works, which you can enter in the chooser.
- 3) If you have printed from MAE
 - If you don't explicitly specify a printer in the print command (the -d option to lp), you may be sending to the wrong printer. UNIX spoolers use an environment variable (LPDEST or PRINTER) to specify your default printer. If the environment variable isn't set, and a printer isn't specified on the command line, then the system default printer is used. The window where you started MAE should have messages saying which printer was used. You can find out the

system default printer with the command "lpstat -d". You can find the value of the environment variables by typing "printenv" in C shell, or "set" in the Bourne or Korn shells.

Note: We recommend having one print command per printer the user prints to, and explicitly specifying the printer, rather than modifying the print command each time.

- Check the UNIX spool print queue:

```
"lpstat -oPRINTERNAME"
```

- Have you changed the print command recently?
- If you have more than one print command entered in the Chooser, do any of them work?
- Did you test printing under UNIX, using the exact same command as in the Chooser?

```
Example: echo "test" | THEIR_CHOOSER_COMMAND
```

- Is the PPD file correct? If it's not, incorrect Postscript may be generated, such as not downloading a font that MAE thinks is resident in the printer, but really isn't. Try using the "generic" PPD (in the "Page Setup" dialog, click on the "Select PPD..." button, then the "use generic" button).
- 4) For some reason, the LprWriter driver may be generating incorrect Postscript. Check that Postscript is actually getting to the printer by doing the following:
- In the "options" dialog of the print dialog (that is, click on the "options" button in the "Print" dialog) specify a cover page to be printed before the document (click on the "Before" radio button).
 - Choose "Postscript Errors - Print detailed report". If the generated Postscript actually makes it to the printer, and it contains a Postscript error, the Postscript error is printed. If nothing is printed, then something else is wrong because Postscript commands aren't getting to the printer.
- 5) If the desktop database (DDB) is bad, peculiar things can happen with printing. The most obvious being the driver not finding the PPD file; the driver stores an alias in the prefs file, and if the DDB is damaged, there's a chance the alias won't resolve. You can check if this is the cause by opening the Chooser, then opening the currently selected print command, and click on "Setup" or just press the <Return> key. If a damaged DDB is the problem, a message similar to what's below appears:

```
"can't find prefs file"
```

```
"can't use PPD file 'XXX', using Generic instead"
```

You need to re-select the PPD file for the printer.

Strange text comes out of the printer, starting with "%!PS-Adobe-3.0"

-
- It's not a Postscript printer.
 - It's a Postscript printer, but the spooling system is interpreting the Postscript as text, instead of a Postscript program to be sent to the printer, and is printing the text of the program. This may be due to an option given to the print command (like the "-p" option with lpr), or it may be due to the spooling system being confused. See your system administrator for help in straightening out this spooling problem.

Can't cancel printing

Before the print status dialog disappears from the MAE window, you can cancel printing by holding down the <Command> and <period> keys at the same time until the "canceling printing" dialog appears. After the printing status dialog disappears from the MAE window, the print request has been given to the user-specified UNIX command for printing. At this point, you must use UNIX commands to cancel printing, for example lprm(1) or cancel(1). For information about using these commands to cancel print requests, see the appropriate man pages in the documentation that came with your workstation, or consult your administrator.

Only the first few pages of the document print

Check to see that the UNIX file systems that contain your MAE system folder (usually your home directory), and the spooling files (usually /usr/spool) aren't full using the df(1) command. If a file system is full, only a portion of your document prints because only a portion of your file was written to disk.

You should see an error message in the window where you started MAE, such as: "no space on device", or "file system full", or "write error". Some files will have to be removed from the file system. See your administrator for help in resolving this problem. Note that some UNIX systems reserve a portion of a file system for the "super user" (up to 10%). The output of df(1) may not indicate that you can no longer add data to the file system.

Can't print from Aldus PageMaker

Aldus PageMaker uses its own, internal Postscript rastering driver instead of using the MAE printer driver. The Aldus driver expects the ability to talk directly to the printer to obtain information about the Postscript version and other parameters. Since MAE uses a user-specified UNIX command for printing, rather than talking to the printer directly, PageMaker cannot print using an Aldus driver. This problem is evidenced by an error message similar to:

"An error occurred while printing. Could not open the printer. Check that the printer connection is correctly set up in the Chooser."

You can print from Aldus PageMaker, but you must use the LprWriter print driver delivered as part of MAE. To do so, hold down the <OPTION> key when selecting

"Print" in PageMaker's "File" menu. This tells PageMaker that you want to use the currently selected, standard driver, rather than an Aldus driver.

Miscellaneous useful commands

To get a list of printers:

```
lpstat -a
```

To get the status for a particular printer:

```
lpstat -oPRINTER
```

```
lpq -PPRINTER
```

Support Information Services

Copyright 1994, Apple Computer, Inc.

Tech Info Library Article Number:15398