



Tech Info Library

HyperCard 2.1: Some Menu Items Can't Be Disabled (& Workaround)

Revised: 7/20/92
Security: Everyone

HyperCard 2.1: Some Menu Items Can't Be Disabled (& Workaround)

=====

Article Created: 1 May 1992
Article Last Reviewed:
Article Last Updated:

TOPIC -----

Some HyperCard 2.1 menu items can't be disabled. For example, the command

```
disable menuItem "New Card" of menu "Edit"
```

doesn't function. This is also true of "Delete Card" and "Cut Card"
An obvious workaround is to DELETE the item instead.

DISCUSSION -----

Claris is aware of the limitation; it is intentional.

There are more elegant workarounds than deleting the menuItem.
The best is to rename the item in question, and then disable it. See the
HyperTalk code below:

```
on openBackground -- or in some other handler
  put "Can't Delete Card" into menuItem "Delete Card" of menu "Edit"
  disable menuItem "Can't Delete Card" of menu "Edit"
end openBackGround
```

This is probably the best way to deal with the issue because it tells the
user specifically that the option isn't available. Otherwise, the user may
wonder if something is wrong with the menu.

You could also add a handler for doMenu...

```
on doMenu which
  if which = "Delete Card"
  then
```

```
        beep -- or put up a dialog informing user
    else
        pass doMenu
    end if
end doMenu
```

Copyright 1992 Apple Computer, Inc.

Tech Info Library Article Number:10162